ezxmltext datatype (XML block)

The ezxmltext datatype (XML block): what it stores and how templates use it.

Source file: doc/eng-us/examples/datatypes/ezxmltext.md Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/datatypes/ezxmltext.md

The ezxmltext datatype (XML block)

Class `eZXMLTextType` in `kernel/classes/datatypes/ezxmltext/ezxmltexttype.php`; identifier `ezxmltext`, listed in `settings/content.ini` `[DataTypeSettings]` `AvailableDataTypes[]`.

What it stores

The columns of the attribute tables its class reads or writes: `data_int`, `data_int1`, `data_text`, `data_text2` (`data_text`, `data_int`, `data_float` and `sort_key_*` are the object attribute's; `data_text1` ... `data_int4` the class attribute's settings). Found by reading the class: a heuristic. It is indexed by the search.

In templates

`my_attribute` stands for the identifier of an attribute of this type in your class:

Template

```
{def $attribute = $node.data_map.my_attribute}
{if $attribute.has_content}
    {attribute_view_gui attribute=$attribute}
{/if}
{* the value as the datatype returns it (objectAttributeContent()) *}
{$attribute.content|attribute( show, 1 )}
```

The shipped template that shows it (`attribute_view_gui`), `design/standard/templates/content/datatype/view/ezxmltext.tpl`:

Template

```
{* DO NOT EDIT THIS FILE! Use an override template instead. *}
{$attribute.content.output.output_text}
```

The shipped template that edits it (`attribute_edit_gui`), `design/standard/templates/content/datatype/edit/ezxmltext.tpl`:

Template

```
{* DO NOT EDIT THIS FILE! Use an override template instead. *}
{default input_handler=$attribute.content.input
         attribute_base='ContentObjectAttribute'}
<textarea id="ezcoa-{if ne( $attribute_base, 'ContentObjectAttribute' )}{$attribute_base}-{/if}{$
attribute.contentclassattribute_id}_{$attribute.contentclass_attribute_identifier}" class="box ez
cc-{$attribute.object.content_class.identifier} ezcca-{$attribute.object.content_class.identifier
}_{$attribute.contentclass_attribute_identifier}" name="{$attribute_base}_data_text_{$attribute.i
d}" cols="97" rows="{$attribute.contentclass_attribute.data_int1}">{$input_handler.input_xml|wash
( xhtml )}</textarea>
{/default}
```

Override them for one class attribute in an `override.ini.append.php` with `Source=content/datatype/view/ezxmltext.tpl` and a match on `attribute_identifier` (see A template override).

Related

- All datatypes
- A custom datatype
- A content class

Generated by `./console exp:help:examples` from `kernel/classes/datatypes/ezxmltext/ezxmltexttype.php`, `settings/content.ini`, `design/standard/templates/content/datatype/view/ezxmltext.tpl`, `design/standard/templates/content/datatype/edit/ezxmltext.tpl`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.