debugbar.ini [Setting_condition_debug]

The settings of [Setting_condition_debug] in debugbar.ini: File, Block, Variable, Type, Label, Group, Help

Source file: `doc/eng-us/examples/ini-settings/debugbar/Setting_condition_debug.md` Last changed 2026-11-04
https://doc.exponential.earth/exphelp/viewer/examples/ini-settings/debugbar/Setting_condition_debug.md

The block `[Setting_condition_debug]` of `settings/debugbar.ini`, with 7 setting(s).

> ---------- conditions, REST, caching

Never edit `settings/debugbar.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/debugbar.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/debugbar.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/debugbar.ini.append.php` in an extension (read when the extension is active).

File

Default: `debug.ini`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_condition_debug]
File=debug.ini
*/ ?>
```

Block

Default: `DebugSettings`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_condition_debug]
Block=DebugSettings
*/ ?>
```

Variable

Default: `ConditionDebug`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_condition_debug]
Variable=ConditionDebug
*/ ?>
```

Type

Default: `bool`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_condition_debug]
Type=bool
*/ ?>
```

Label

Default: `Conditional debug`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_condition_debug]
Label=Conditional debug
*/ ?>
```

Group

Default: `conditions`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_condition_debug]
Group=conditions
*/ ?>
```

Help

Default: `Master switch of the debug conditions below (debug.ini GeneralCondition).`

.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_condition_debug]
Help=Master switch of the debug conditions below (debug.ini GeneralCondition).
*/ ?>
```

Related

- All blocks of debugbar.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/debugbar.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.