content.ini [TestingSettings]

The settings of [TestingSettings] in content.ini: MultivariateTesting, MultivariateTestingHandlerClass, EnabledForSiteAccessList

Source file: `doc/eng-us/examples/ini-settings/content/TestingSettings.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/content/TestingSettings.md

The block `[TestingSettings]` of `settings/content.ini`, with 3 setting(s).

Never edit `settings/content.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/content.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/content.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/content.ini.append.php` in an extension (read when the extension is active).

MultivariateTesting

> Enable or disable multivariate testing feature

Default: `disabled`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/content.ini.append.php
[TestingSettings]
MultivariateTesting=disabled
*/ ?>
```

MultivariateTestingHandlerClass

> A handler class which implements <ezpMultivariateTestHandlerInterface> interface

Default: `ezpMultivariateTestHandler`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/content.ini.append.php
[TestingSettings]
MultivariateTestingHandlerClass=ezpMultivariateTestHandler
*/ ?>
```

EnabledForSiteAccessList

> List of site accesses multivariate testing is enabled for.

Default: an empty list.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/content.ini.append.php
[TestingSettings]
# an empty "EnabledForSiteAccessList[]" first replaces the shipped list; without it the items are
 added
EnabledForSiteAccessList[]
*/ ?>
```

Related

- All blocks of content.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/content.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.