datatable.ini [ConnectionSettings]

The settings of [ConnectionSettings] in datatable.ini: Engines, SQLiteDirectories, AllowedHosts, ConnectTimeout

Source file: `doc/eng-us/examples/ini-settings/datatable/ConnectionSettings.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/datatable/ConnectionSettings.md

The block `[ConnectionSettings]` of `settings/datatable.ini`, with 4 setting(s).

Never edit `settings/datatable.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/datatable.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/datatable.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/datatable.ini.append.php` in an extension (read when the extension is active).

Engines

> The engines that may be used for a connection (sqlite, mysql, postgresql, oracle, sqlserver, mongodb)

Default: a list of 6: `sqlite`, `mysql`, `postgresql`, `oracle`, `sqlserver`, `mongodb`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/datatable.ini.append.php
[ConnectionSettings]
# an empty "Engines[]" first replaces the shipped list; without it the items are added
Engines[]
Engines[]=sqlite
Engines[]=mysql
Engines[]=postgresql
Engines[]=oracle
Engines[]=sqlserver
Engines[]=mongodb
*/ ?>
```

SQLiteDirectories

> The directories a SQLite connection's file may be in, relative to the installation; the file is created there
> when it does not exist yet. A path outside them is refused.

Default: a list of 1: `var/datatable`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/datatable.ini.append.php
[ConnectionSettings]
# an empty "SQLiteDirectories[]" first replaces the shipped list; without it the items are added
SQLiteDirectories[]
SQLiteDirectories[]=var/datatable
*/ ?>
```

AllowedHosts

> Hosts a server connection may reach, besides any when the list is empty (host names or addresses; * for any)

Default: an empty list.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/datatable.ini.append.php
[ConnectionSettings]
# an empty "AllowedHosts[]" first replaces the shipped list; without it the items are added
AllowedHosts[]
*/ ?>
```

ConnectTimeout

> Seconds a connection test waits for the server

Default: `5`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/datatable.ini.append.php
[ConnectionSettings]
ConnectTimeout=5
*/ ?>
```

Related

- All blocks of datatable.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/datatable.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:

https://www.gnu.org/licenses/fdl-1.3.html.