# error.ini [ErrorSettings]

The settings of [ErrorSettings] in error.ini: DefaultErrorHandler, DefaultRedirectURL, DefaultRerunURL, DefaultEmbedURL

Source file: `doc/eng-us/examples/ini-settings/error/ErrorSettings.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/error/ErrorSettings.md

The block `[ErrorSettings]` of `settings/error.ini`, with 4 setting(s).

> Global error settings which are used for all error types
> A specific error type group is defined with ErrorSettings followed
> by a - (dash) and the error type name, e.g. ErrorSettting-kernel

Never edit `settings/error.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/error.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/error.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/error.ini.append.php` in an extension (read when the extension is active).

## DefaultErrorHandler

> Static pages for failures outside the template engine (lib/ezutils/classes/ezexecution.php):
> StaticErrorPage[500], StaticErrorPage[503], StaticErrorPage[default], and one per known error
> case, shown instead of the general page when the installation explains the failure:
> StaticErrorPage[dependencies] the Composer libraries (vendor/) are missing; placeholders {status} {title} {message} {steps} {repair} {reference} {home} {detail}. Unset: a built-in page.
> StaticErrorPage[dependencies]=design/standard/errors/dependencies.html
> Which handler to use, possible handlers are:
> displayerror - Displays a text explaining the error
> redirect - Redirect to a specific url
> rerun - Rerun a module/view on the page, specified by a url
> embed - Run a module/view and embed the results on the
> same page used in displayerror

Default: `displayerror`.

**INI**

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/error.ini.append.php
[ErrorSettings]
DefaultErrorHandler=displayerror
*/ ?>
```

## DefaultRedirectURL

Default: `/content/view/full/2`.

**INI**

```
<?php /* #?ini charset="utf-8"?
# settings/override/error.ini.append.php
[ErrorSettings]
DefaultRedirectURL=/content/view/full/2
*/ ?>
```

## DefaultRerunURL

Default: `/content/view/full/2`.

**INI**

```
<?php /* #?ini charset="utf-8"?
# settings/override/error.ini.append.php
[ErrorSettings]
DefaultRerunURL=/content/view/full/2
*/ ?>
```

## DefaultEmbedURL

Default: `/user/login`.

**INI**

```
<?php /* #?ini charset="utf-8"?
# settings/override/error.ini.append.php
[ErrorSettings]
DefaultEmbedURL=/user/login
*/ ?>
```

## Related

- All blocks of error.ini
- All INI files
- The settings page

---

Generated by `./console exp:help:examples` from `settings/error.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

---

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.