content_version_view_gui template function

The content_version_view_gui template function, registered by eZObjectForwarder.

Source file: `doc/eng-us/examples/template-functions/content_version_view_gui.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/template-functions/content_version_view_gui.md

The content_version_view_gui template function

Registered in `kernel/common/eztemplateautoload.php` by the class `eZObjectForwarder` (`kernel/common/ezobjectforwarder.php`). The same class also handles: attribute_edit_gui, attribute_view_gui, attribute_result_gui, attribute_pdf_gui, attribute_diff_gui, related_view_gui, node_view_gui, content_view_gui, content_pdf_gui, shop_account_view_gui, collaboration_view_gui, collaboration_icon, collaboration_simple_message_view, collaboration_participation_view, event_edit_gui, event_view_gui, class_attribute_view_gui, class_attribute_edit_gui.

How it finds its template

From the forward rule in `eZObjectForwardInit()` (`kernel/common/eztemplateautoload.php`):

Key	Value
template_root	'content/version/view'
input_name	'content_version'
output_name	'version'
namespace	'VersionView'
use_views	'view'
override match keys	object, class, section, class_identifier

Template

```
{content_version_view_gui content_version=$content_version view=view}
```

The variable name is the rule's `input_name`; the value is a placeholder.

In a shipped template

The first use in the templates of this installation, `design/admin/templates/collaboration/handlers/view/full/ezapprove.tpl` line 13:

Template

```
{content_version_view_gui view=text_linked content_version=$content_version}
```

Related

- All template functions
- Template operators
- Templates and design

Generated by `./console exp:help:examples` from `kernel/common/eztemplateautoload.php`, `kernel/common/ezobjectforwarder.php`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.