exp:expusershow

Source file: doc/eng-us/examples/commands/expusershow.md Last changed 2026-11-04
https://doc.exponential.earth/exphelp/viewer/examples/commands/expusershow.md

Show one user account: groups, roles with their limitation, enabled or locked, last visit, registration state, two-step sign-in and active sessions (never a password hash).

Script `bin/php/expusershow.php`, code in `kernel/private/classes/commands/expusershow.php`. Run it from the installation root, as the user the web server runs as:

Shell

```
./console exp:expusershow --help
./console exp:user:show --help
php bin/php/expusershow.php --help
```

Help text

```
Show one user account
Names the account by its login, its e-mail address (when one account has it) or its id, and
shows its groups (the main one first), its roles with where they come from and their limitation,
whether it is enabled, unactivated or locked, its sign-ins and last visit, the state of its
registration, two-step sign-in, active sessions, whether a new password is required, and whether
the account is protected from being disabled or removed. Never a password hash. Changes nothing.

./console exp:user:show admin
./console exp:user:show jane@example.com --format=json
./console exp:user:show 14
```

Options

Option	Value	Help
`--as`	required	Act as this user (login, e-mail or id; default the user of [UserSettings] UserCreatorID); the audit records it as who did it
`--format`	required	text (default) or json (the machine output exp-user/1)

Read from the option definitions in the code (`startup()`, `getOptions()`, `options()` or `ezcConsoleOption`). Every script also takes the standard options of the script framework (`--help`, `--siteaccess`, `--debug`, `--quiet`, `--allow-root-user` ...).

Arguments: `[user]`.

Related

- All console commands

Generated by `./console exp:help:examples` from `bin/php/expusershow.php`, `kernel/private/classes/commands/expusershow.php`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.