browse.ini [AddPrimaryNodeAssignment]

The settings of [AddPrimaryNodeAssignment] in browse.ini: StartNode, SelectionType, ReturnType, StartNode_classgroup

Source file: `doc/eng-us/examples/ini-settings/browse/AddPrimaryNodeAssignment.md` Last changed 2026-11-04
https://doc.exponential.earth/exphelp/viewer/examples/ini-settings/browse/AddPrimaryNodeAssignment.md

The block `[AddPrimaryNodeAssignment]` of `settings/browse.ini`, with 4 setting(s).

> Action for selecting a node placement for an object.

Never edit `settings/browse.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/browse.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/browse.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/browse.ini.append.php` in an extension (read when the extension is active).

StartNode

Default: `content`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/browse.ini.append.php
[AddPrimaryNodeAssignment]
StartNode=content
*/ ?>
```

SelectionType

Default: `multiple`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/browse.ini.append.php
[AddPrimaryNodeAssignment]
SelectionType=multiple
*/ ?>
```

ReturnType

Default: `NodeID`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/browse.ini.append.php
[AddPrimaryNodeAssignment]
ReturnType=NodeID
*/ ?>
```

StartNode_classgroup

Default: a hash of 1: `2=users`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/browse.ini.append.php
[AddPrimaryNodeAssignment]
# an empty "StartNode_classgroup[]" first replaces the shipped list; without it the items are add
ed
StartNode_classgroup[]
StartNode_classgroup[2]=users
*/ ?>
```

Related

- All blocks of browse.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/browse.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.