/package/install

The view package/install: its address, parameters and the policy functions it needs.

Source file: doc/eng-us/examples/module-views/package/install.md Last changed 2026-11-04
https://doc.exponential.earth/exphelp/viewer/examples/module-views/package/install.md

A view of the `package` module, defined in `kernel/package/module.php` and run by `kernel/package/install.php`.

Address

```
/package/install/<PackageName>
```

Ordered parameters, in this order after the view name: `PackageName`.

Who may open it

The user needs this policy function:

- `package/install`

A policy on `package/*` (every function) also grants it; limitations of the policy (section, subtree, class ...) still apply where the view checks them.

Details

Key	Value
Navigation part	`ezsetupnavigationpart`
UI context	`edit`
Single POST actions	HandleError: HandleError, InstallPackageButton: InstallPackage, PackageStep: PackageStep, SkipPackageButton: SkipPackage
POST action parameters	InstallPackage (InstallerType: InstallerType, AsDrafts: AsDrafts, DraftsExisting: DraftsExisting, Background: Background), PackageStep (InstallerType: InstallerType, InstallStepID: InstallStepID, PreviousStep: PreviousStepButton, NextStep: NextStepButton), HandleError (ActionID: ActionID, RememberAction: RememberAction)

Example

A link in a template (`ezurl` adds the siteaccess and quotes the address); the parameter values are placeholders:

Template

```
<a href={'/package/install/packagename'|ezurl}>package/install</a>
```

From PHP, the redirect a view gives after it has done its work:

PHP

```php
return $Module->redirectTo( '/package/install/packagename' );
```

Related

- All views of package
- The policies of package
- A custom module and view

Generated by `./console exp:help:examples` from `kernel/package/module.php`, `kernel/package/install.php`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.