exp:accesscheck

Source file: doc/eng-us/examples/commands/accesscheck.md Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/commands/accesscheck.md

Check what a user may do with a node or object (content/read, edit, ...) and which limitation refuses it.

Script `bin/php/accesscheck.php`, code in `kernel/private/classes/commands/accesscheck.php`. Run it from the installation root, as the user the web server runs as:

Shell

```
./console exp:accesscheck --help
./console exp:access:check --help
php bin/php/accesscheck.php --help
```

Help text

```
Access check for a user
Whether a user may read, edit, remove ... a node or an object, decided as the views decide
it, and when not, the policies and the limitation that refused, those of extensions
included. Nobody signs in and nothing is changed.

./console exp:access:check --user=editor --node=2
./console exp:access:check --user=14 --object=57 --function=edit --language=eng-GB
./console exp:access:check --user=anonymous --node=2 --json

Functions:
```

Options

Option	Value	Help
`--user`	required	The user: its content object ID or its login; "anonymous" for the anonymous user
`--node`	required	The node ID to check
`--object`	required	The object ID to check (instead of a node)
`--function`	required	The content function (default read)
`--language`	required	A language code, for edit and translate
`--json`		One JSON object instead of the text

Read from the option definitions in the code (`startup()`, `getOptions()`, `options()` or `ezcConsoleOption`). Every script also takes the standard options of the script framework (`--help`, `--siteaccess`, `--debug`, `--quiet`, `--allow-root-user` ...).

Related

- All console commands

Generated by `./console exp:help:examples` from `bin/php/accesscheck.php`, `kernel/private/classes/commands/accesscheck.php`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.