exp:expurlundo

Source file: doc/eng-us/examples/commands/expurlundo.md Last changed 2026-11-06
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/commands/expurlundo.md

Undo a URL map import: every alias, wildcard and redirect it created or changed back as it was.

Script `bin/php/expurlundo.php`, code in `kernel/private/classes/commands/expurlundo.php`. Run it from the installation root, as the user the web server runs as:

Shell

```
./console exp:expurlundo --help
./console exp:url:undo --help
php bin/php/expurlundo.php --help
```

Help text

```
Undo a URL map import
Puts every URL alias, wildcard and redirect the import created or changed back as it was before,
the
last first, in one transaction. An entry changed after the import is kept (the batch is then
partly-undone), unless --force is given. exp:url:batches lists the imports.

./console exp:url:undo 12
./console exp:url:undo 12 --force --format=json
```

Options

Option	Value	Help
`--force`		Undo also the entries that changed after the import (default: they are kept)
`--format`	required	import: the format of the file (csv, json, xlsx, ods, apache, nginx; default from its name or content); export: the format to write (default from --output, else csv); batches, undo, from-sitemap, from-404, suggest, test: text (default) or json (the machine output exp-url/1)
`--login`	required	Run as this user (recorded with the import and in the audit)

Read from the option definitions in the code (`startup()`, `getOptions()`, `options()` or `ezcConsoleOption`). Every script also takes the standard options of the script framework (`--help`, `--siteaccess`, `--debug`, `--quiet`, `--allow-root-user` ...).

Arguments: `[batch]`.

Related

- All console commands

Generated by `./console exp:help:examples` from `bin/php/expurlundo.php`, `kernel/private/classes/commands/expurlundo.php`. Do not edit this page: change the

source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.