admininterface.ini [AdditionalTab_datatable]

The settings of [AdditionalTab_datatable] in admininterface.ini: Title, Description, NavigationPartName, HeaderTemplate, Template

Source file: `doc/eng-us/examples/ini-settings/admininterface/AdditionalTab_datatable.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/admininterface/AdditionalTab_datatable.md

The block `[AdditionalTab_datatable]` of `settings/admininterface.ini`, with 5 setting(s).

Never edit `settings/admininterface.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/admininterface.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/admininterface.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/admininterface.ini.append.php` in an extension (read when the extension is active).

Title

Default: empty.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/admininterface.ini.append.php
[AdditionalTab_datatable]
Title=
*/ ?>
```

Description

Default: empty.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/admininterface.ini.append.php
[AdditionalTab_datatable]
Description=
*/ ?>
```

NavigationPartName

Default: `ezcontentnavigationpart`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/admininterface.ini.append.php
[AdditionalTab_datatable]
NavigationPartName=ezcontentnavigationpart
*/ ?>
```

HeaderTemplate

Default: `datatable/node_header.tpl`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/admininterface.ini.append.php
[AdditionalTab_datatable]
HeaderTemplate=datatable/node_header.tpl
*/ ?>
```

Template

Default: `datatable/node.tpl`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/admininterface.ini.append.php
[AdditionalTab_datatable]
Template=datatable/node.tpl
*/ ?>
```

Related

- All blocks of admininterface.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/admininterface.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.