admininterface.ini [SubItems]

The settings of [SubItems] in admininterface.ini: VisibleColumns

Source file: doc/eng-us/examples/ini-settings/admininterface/SubItems.md Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/admininterface/SubItems.md

The block `[SubItems]` of `settings/admininterface.ini`, with 1 setting(s).

> Example settings used in the OpenOffice.org extension
> ContextMenuTemplateArray[]=node/oocontextmenu.tpl
> SubitemsContextMenuTemplateArray[]=node/oosubitemscontextmenu.tpl
> Default setting for subitems table

Never edit `settings/admininterface.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/admininterface.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/admininterface.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/admininterface.ini.append.php` in an extension (read when the extension is active).

VisibleColumns

> Column names reflect the attribute names of template variable $node

Default: a hash of 3: `ezcontentnavigationpart=checkbox;crank;name;published_date;translations;priority`, `ezmedianavigationpart=checkbox;crank;thumbnail;name;hidden_status_string;class_name`, `ezusernavigationpart=checkbox;crank;name;creator;published_date`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/admininterface.ini.append.php
[SubItems]
# an empty "VisibleColumns[]" first replaces the shipped list; without it the items are added
VisibleColumns[]
VisibleColumns[ezcontentnavigationpart]=checkbox;crank;name;published_date;translations;priority
VisibleColumns[ezmedianavigationpart]=checkbox;crank;thumbnail;name;hidden_status_string;class_na
me
VisibleColumns[ezusernavigationpart]=checkbox;crank;name;creator;published_date
*/ ?>
```

Related

- All blocks of admininterface.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/admininterface.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.