content.ini [RelationAssignmentSettings]

The settings of [RelationAssignmentSettings] in content.ini: DefaultAssignment, ClassSpecificAssignment

Source file: `doc/eng-us/examples/ini-settings/content/RelationAssignmentSettings.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/content/RelationAssignmentSettings.md

The block `[RelationAssignmentSettings]` of `settings/content.ini`, with 2 setting(s).

Never edit `settings/content.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/content.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/content.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/content.ini.append.php` in an extension (read when the extension is active).

DefaultAssignment

> Default assignment for new related objects, possible values are
>
> - A Node ID - Place all new objects under this node
> - A node path - The placement of the parent node by a path, e.g. media/files
> - root - The root of the tree
> - users - The root of the user tree
> - media - The root of the media tree
> - none - DEPRECATED
>
> Multiple assignments are not allowed.

Default: `root`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/content.ini.append.php
[RelationAssignmentSettings]
DefaultAssignment=root
*/ ?>
```

ClassSpecificAssignment

> Automatic assignments for specific classes.
>
> Each line consists of three or two values separated by semi-colon.
> First two values are lists of elements which are comma separated.
>
> First value is the class identifier, second is the assignment (see above for

> values). An optional third is the main node in case you upload to many locations. If the third parameter is not set, then the first element of the value 2 will be used as main node.
>
> Classes are either specified with identifier, ID or group_ID
> The items are searched in order so the first to match will be used, this means that class IDs should come before class group IDs.
>
> If the same class is specified in many lines, then will be used the first match where user has an access to all listed nodes.

Default: a list of 8: `user,user_group;users/guest_accounts`, `image;media/images`, `video;media/multimedia`, `file;media/files`, `quicktime;media/multimedia`, `windows_media;media/multimedia`, `real_video;media/multimedia`, `flash;media/multimedia`.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/content.ini.append.php
[RelationAssignmentSettings]
# an empty "ClassSpecificAssignment[]" first replaces the shipped list; without it the items are
added
ClassSpecificAssignment[]
ClassSpecificAssignment[]=user,user_group;users/guest_accounts
ClassSpecificAssignment[]=image;media/images
ClassSpecificAssignment[]=video;media/multimedia
ClassSpecificAssignment[]=file;media/files
ClassSpecificAssignment[]=quicktime;media/multimedia
ClassSpecificAssignment[]=windows_media;media/multimedia
ClassSpecificAssignment[]=real_video;media/multimedia
ClassSpecificAssignment[]=flash;media/multimedia
*/ ?>
```

Related

- All blocks of content.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/content.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.