content.ini [VersionView]

The settings of [VersionView] in content.ini: AvailableSiteDesignList, ViewModes

Source file: doc/eng-us/examples/ini-settings/content/VersionView.md Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/content/VersionView.md

The block `[VersionView]` of `settings/content.ini`, with 2 setting(s).

Never edit `settings/content.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/content.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/content.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/content.ini.append.php` in an extension (read when the extension is active).

AvailableSiteDesignList

> OBSOLETE: Use AvailableSiteDesignList instead
> Specify all available site designs
> AvailableSiteDesigns=standard;user;admin;demo
> OBSOLETE: A list of designs the site can use

Default: a list of 1: `admin`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/content.ini.append.php
[VersionView]
# an empty "AvailableSiteDesignList[]" first replaces the shipped list; without it the items are
added
AvailableSiteDesignList[]
AvailableSiteDesignList[]=admin
*/ ?>
```

ViewModes

> AvailableSiteDesignList[]=base
> The view modes a version can be shown in,
> content/versionview/<object>/<version>/(view_mode)/<mode>
> (node/view/<mode>.tpl); another one is not available. Without the parameter it is full.
> With more than one listed, the View control box of the preview in the admin offers them.
> design/standard has node/view/print.tpl as an example of a print layout.

Default: a list of 1: `full`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/content.ini.append.php
[VersionView]
# an empty "ViewModes[]" first replaces the shipped list; without it the items are added
ViewModes[]
ViewModes[]=full
*/ ?>
```

Related

- All blocks of content.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/content.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.