content.ini [embed-inline]

The settings of [embed-inline] in content.ini: AvailableViewModes, AvailableClasses, CustomAttributes

Source file: doc/eng-us/examples/ini-settings/content/embed-inline.md Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/content/embed-inline.md

The block `[embed-inline]` of `settings/content.ini`, with 3 setting(s).

Never edit `settings/content.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/content.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/content.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/content.ini.append.php` in an extension (read when the extension is active).

AvailableViewModes

Default: an empty list.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/content.ini.append.php
[embed-inline]
# an empty "AvailableViewModes[]" first replaces the shipped list; without it the items are added
AvailableViewModes[]
*/ ?>
```

AvailableClasses

Default: an empty list.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/content.ini.append.php
[embed-inline]
# an empty "AvailableClasses[]" first replaces the shipped list; without it the items are added
AvailableClasses[]
*/ ?>
```

CustomAttributes

> AvailableClasses[]=embedRed
> AvailableClasses[]=embedBlue

Default: an empty list.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/content.ini.append.php
[embed-inline]
# an empty "CustomAttributes[]" first replaces the shipped list; without it the items are added
CustomAttributes[]
*/ ?>
```

Related

- All blocks of content.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/content.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.