debugbar.ini [Preset_sql_tuning]

The settings of [Preset_sql_tuning] in debugbar.ini: Name, Description, Values

Source file: doc/eng-us/examples/ini-settings/debugbar/Preset_sql_tuning.md Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/debugbar/Preset_sql_tuning.md

The block `[Preset_sql_tuning]` of `settings/debugbar.ini`, with 3 setting(s).

Never edit `settings/debugbar.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/debugbar.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/debugbar.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/debugbar.ini.append.php` in an extension (read when the extension is active).

Name

Default: `SQL tuning`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Preset_sql_tuning]
Name=SQL tuning
*/ ?>
```

Description

Default: `Every statement with its time, the analysis, and transaction debug.`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Preset_sql_tuning]
Description=Every statement with its time, the analysis, and transaction debug.
*/ ?>
```

Values

Default: a hash of 4: `debug_output=on`, `sql_output=on`, `sql_query_analysis=on`, `sql_debug_transactions=on`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Preset_sql_tuning]
# an empty "Values[]" first replaces the shipped list; without it the items are added
Values[]
Values[debug_output]=on
Values[sql_output]=on
Values[sql_query_analysis]=on
Values[sql_debug_transactions]=on
*/ ?>
```

Related

- All blocks of debugbar.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/debugbar.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.