debugbar.ini

The blocks and settings of debugbar.ini.

Source file: `doc/eng-us/examples/ini-settings/debugbar/README.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/debugbar/README.md

The shipped settings of `settings/debugbar.ini`: 42 blocks, 292 settings.

> The registry of the Exp Debug bar (the pinned bar at the bottom of a page with debug output).
> Guide: doc/eng-us/bc/6.0/debug-bar.md
>
> Every setting the bar shows and changes is one [Setting_<id>] block:
>
> [Setting_<id>]
> File=site.ini the INI file
> Block=DebugSettings its block
> Variable=DebugOutput its variable
> Type=bool bool | enum | list | text | iplist | userlist
> Label=Debug output
> Group=output one of [DebugBarSettings] Groups[]
> Help=One sentence on what it does.
> Values[] enum only: the values it may take
> On=enabled bool only: the words written for on and off; default: the words the
> Off=disabled setting's own default uses (enabled/disabled or true/false)
>
> Every write goes through the exp:ini engine (expIniEditor): line by line, with a backup, keeping
> the file's owner. An extension adds its own settings in its
> settings/debugbar.ini.append.php:
>
> [DebugBarSettings]
> Settings[]=myext_debug
> [Setting_myext_debug]
> File=myext.ini
> ...

Block	Settings
DebugBarSettings	18
Setting_debug_output	7
Setting_debug_mode	8
Setting_debug_redirection	7
Setting_display_debug_warnings	7
Setting_debug_log_only	7
Setting_display_included_files	7
Setting_always_log	8
Setting_deprecated_log	7

Block	Settings
Setting_script_debug_output	7
Setting_debug_toolbar	7
Setting_debug_bar_theme	8
Setting_debug_by_ip	7
Setting_debug_ip_list	7
Setting_debug_by_user	7
Setting_debug_user_list	7
Setting_template_debug	7
Setting_template_show_xhtml_code	7
Setting_template_show_used_templates	7
Setting_template_path_comments	7
Setting_template_show_method_debug	7
Setting_template_development_mode	7
Setting_template_compile	7
Setting_template_cache	7
Setting_template_compile_accumulators	7
Setting_template_compile_timing_points	7
Setting_template_compile_comments	7
Setting_sql_output	7
Setting_sql_query_analysis	7
Setting_sql_slow_queries	7
Setting_sql_debug_transactions	7
Setting_regional_debug	7
Setting_regional_development_mode	7
Setting_mail_debug_sending	7
Setting_mail_debug_receiver	7
Setting_condition_debug	7
Setting_rest_debug	7
Setting_content_view_caching	7
Preset_template_work	3
Preset_sql_tuning	3
Preset_everything	3
Preset_off	3

- All examples

Generated by `./console exp:help:examples` from `settings/debugbar.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.