# debugbar.ini [Setting_debug_ip_list]

The settings of [Setting_debug_ip_list] in debugbar.ini: File, Block, Variable, Type, Label, Group, Help

Source file: `doc/eng-us/examples/ini-settings/debugbar/Setting_debug_ip_list.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/debugbar/Setting_debug_ip_list.md

The block `[Setting_debug_ip_list]` of `settings/debugbar.ini`, with 7 setting(s).

Never edit `settings/debugbar.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/debugbar.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/debugbar.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/debugbar.ini.append.php` in an extension (read when the extension is active).

## File

Default: `site.ini`.

**INI**

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_debug_ip_list]
File=site.ini
*/ ?>
```

## Block

Default: `DebugSettings`.

**INI**

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_debug_ip_list]
Block=DebugSettings
*/ ?>
```

## Variable

Default: `DebugIPList`.

**INI**

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_debug_ip_list]
Variable=DebugIPList
*/ ?>
```

## Type

Default: `iplist`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_debug_ip_list]
Type=iplist
*/ ?>
```

## Label

Default: `IP list`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_debug_ip_list]
Label=IP list
*/ ?>
```

## Group

Default: `access`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_debug_ip_list]
Group=access
*/ ?>
```

## Help

Default: `IPv4 and IPv6 addresses and networks (CIDR), each with an optional label and expiry.`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/debugbar.ini.append.php
[Setting_debug_ip_list]
Help=IPv4 and IPv6 addresses and networks (CIDR), each with an optional label and expiry.
*/ ?>
```

## Related

- All blocks of debugbar.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/debugbar.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.