logfile.ini [AccessLogFileSettings]

The settings of [AccessLogFileSettings] in logfile.ini: StorageDir, LogFileName, SitePrefix, PathPrefix, Host, Port, Hosts

Source file: `doc/eng-us/examples/ini-settings/logfile/AccessLogFileSettings.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/logfile/AccessLogFileSettings.md

The block `[AccessLogFileSettings]` of `settings/logfile.ini`, with 7 setting(s).

Never edit `settings/logfile.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/logfile.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/logfile.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/logfile.ini.append.php` in an extension (read when the extension is active).

StorageDir

> The access log of a siteaccess. Set it in settings/override for a log every siteaccess shares, or in settings/siteaccess/<siteaccess>/logfile.ini.append.php for a log of one siteaccess.
> Storage of the log file, for example /var/log/httpd
> Do not add trailing slash

Default: empty.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/logfile.ini.append.php
[AccessLogFileSettings]
StorageDir=
*/ ?>
```

LogFileName

> The name of log file, for example mytest.log

Default: empty.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/logfile.ini.append.php
[AccessLogFileSettings]
LogFileName=
*/ ?>
```

SitePrefix

> If using site match by URL, the site may like http://siteurl/mysite and
> apache log will start with for example mysite/content/view/full/node_id. To
> remove this prefix in apache log before analysis the log, add mysite to
> SitePrefix. Example: SitePrefix[]=mysite
> Only a whole first path element is removed. When several counted siteaccesses share the log,
> the siteaccess matching removes the siteaccess's part of the path instead.

Default: a list of 1: ``.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/logfile.ini.append.php
[AccessLogFileSettings]
# an empty "SitePrefix[]" first replaces the shipped list; without it the items are added
SitePrefix[]
SitePrefix[]=
*/ ?>
```

PathPrefix

> If any site accesses use the PathPrefix setting, enter them here
> A path is looked up with each prefix in front first, then as it is. Empty: the PathPrefix
> of the siteaccess's site.ini [SiteAccessSettings].

Default: a list of 1: ``.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/logfile.ini.append.php
[AccessLogFileSettings]
# an empty "PathPrefix[]" first replaces the shipped list; without it the items are added
PathPrefix[]
PathPrefix[]=
*/ ?>
```

Host

> The host the log's requests were made to, for the siteaccess matching, when its lines do not
> name one (the common and combined formats do not; vhost_combined does). Example: www.example.com

Default: empty.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/logfile.ini.append.php
[AccessLogFileSettings]
Host=
*/ ?>
```

Port

> The port of the log's requests, for MatchOrder=port. Empty: 80.

Default: empty.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/logfile.ini.append.php
[AccessLogFileSettings]
Port=
*/ ?>
```

Hosts

> Only lines of these hosts are counted for the siteaccess (a line that names no host takes Host). Empty: every host. Example: Hosts[]=www.example.com

Default: an empty list.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/logfile.ini.append.php
[AccessLogFileSettings]
# an empty "Hosts[]" first replaces the shipped list; without it the items are added
Hosts[]
*/ ?>
```

Related

- All blocks of logfile.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/logfile.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.