requestclassifier.ini [RuleSet-traversal]

The settings of [RuleSet-traversal] in requestclassifier.ini: Class, Patterns, Disabled

Source file: `doc/eng-us/examples/ini-settings/requestclassifier/RuleSet-traversal.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/requestclassifier/RuleSet-traversal.md

The block `[RuleSet-traversal]` of `settings/requestclassifier.ini`, with 3 setting(s).

Never edit `settings/requestclassifier.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/requestclassifier.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/requestclassifier.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/requestclassifier.ini.append.php` in an extension (read when the extension is active).

Class

> Matched against the raw URI and the URI decoded once. Rules: double-encoded (%252e), null-byte (%00),
> encoded-dot-dot (%2e%2e, ..%2f in any case), dot-dot (../ and ..\).

Default: empty.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/requestclassifier.ini.append.php
[RuleSet-traversal]
Class=
*/ ?>
```

Patterns

Default: an empty list.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/requestclassifier.ini.append.php
[RuleSet-traversal]
# an empty "Patterns[]" first replaces the shipped list; without it the items are added
Patterns[]
*/ ?>
```

Disabled

Default: an empty list.

INI

```
<?php /* #?ini charset="utf-8"?
# settings/override/requestclassifier.ini.append.php
[RuleSet-traversal]
# an empty "Disabled[]" first replaces the shipped list; without it the items are added
Disabled[]
*/ ?>
```

Related

- All blocks of requestclassifier.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/requestclassifier.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.