template.ini [AttributeOperator]

The settings of [AttributeOperator] in template.ini: DefaultFormatter, OutputFormatter

Source file: `doc/eng-us/examples/ini-settings/template/AttributeOperator.md` Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/ini-settings/template/AttributeOperator.md

The block `[AttributeOperator]` of `settings/template.ini`, with 2 setting(s).

> To create custom tag list send the name of this list as the first parameter to simpletags, e.g simpletags('mytags'), then create a list named TagList_<yourname> where <yourname> is the name of the tag list
> Example:
> TagList_mytags[]
> Configuration for the 'attribute' template operator

Never edit `settings/template.ini` itself: an update replaces it. Put the settings you change in an override, which wins over the shipped file:

- `settings/override/template.ini.append.php` for every siteaccess,
- `settings/siteaccess/<siteaccess>/template.ini.append.php` for one siteaccess,
- `extension/<extension>/settings/template.ini.append.php` in an extension (read when the extension is active).

DefaultFormatter

Default: `html`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/template.ini.append.php
[AttributeOperator]
DefaultFormatter=html
*/ ?>
```

OutputFormatter

Default: a hash of 2: `html=ezpAttributeOperatorHTMLFormatter`, `text=ezpAttributeOperatorTextFormatter`.

INI

```ini
<?php /* #?ini charset="utf-8"?
# settings/override/template.ini.append.php
[AttributeOperator]
# an empty "OutputFormatter[]" first replaces the shipped list; without it the items are added
OutputFormatter[]
OutputFormatter[html]=ezpAttributeOperatorHTMLFormatter
OutputFormatter[text]=ezpAttributeOperatorTextFormatter
*/ ?>
```

Related

- All blocks of template.ini
- All INI files
- The settings page

Generated by `./console exp:help:examples` from `settings/template.ini`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.