/ezoe/engine

The view ezoe/engine: its address, parameters and the policy functions it needs.

Source file: doc/eng-us/examples/module-views/ezoe/engine.md Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/module-views/ezoe/engine.md

A view of the `ezoe` module, defined in `extension/ezoe/modules/ezoe/module.php` and run by `extension/ezoe/modules/ezoe/engine.php`.

Address

```
/ezoe/engine
```

Who may open it

The user needs this policy function:

- `ezoe/editor`

A policy on `ezoe/*` (every function) also grants it; limitations of the policy (section, subtree, class ...) still apply where the view checks them.

Details

Key	Value
UI context	`administration`
Single POST actions	SaveEngineButton: Save
POST action parameters	Save (Engine: Engine)

Example

A link in a template (`ezurl` adds the siteaccess and quotes the address); the parameter values are placeholders:

Template

```
<a href={'/ezoe/engine'|ezurl}>ezoe/engine</a>
```

From PHP, the redirect a view gives after it has done its work:

PHP

```
return $Module->redirectTo( '/ezoe/engine' );
```

Related

- All views of ezoe
- The policies of ezoe

- A custom module and view

Generated by `./console exp:help:examples` from `extension/ezoe/modules/ezoe/module.php`, `extension/ezoe/modules/ezoe/engine.php`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.