/setup/rad

The view setup/rad: its address, parameters and the policy functions it needs.

Source file: doc/eng-us/examples/module-views/setup/rad.md Last changed 2026-11-04
https://doc.exponential.earth/learninminutes/exphelp/viewer/examples/module-views/setup/rad.md

A view of the `setup` module, defined in `kernel/setup/module.php` and run by `kernel/setup/rad.php`.

Address

```
/setup/rad/(show)/<Show>
```

Unordered parameters, in any order as `/(name)/value`: `(show)` sets `Show`.

Who may open it

The user needs this policy function:

- `setup/setup`

A policy on `setup/*` (every function) also grants it; limitations of the policy (section, subtree, class ...) still apply where the view checks them.

Details

Key	Value
Navigation part	`ezsetupnavigationpart`
UI context	`administration`

Example

A link in a template (`ezurl` adds the siteaccess and quotes the address); the parameter values are placeholders:

Template

```
<a href={'/setup/rad'|ezurl}>setup/rad</a>
<a href={concat( '/setup/rad/(show)/', 1 )|ezurl}>setup/rad</a>
```

From PHP, the redirect a view gives after it has done its work:

PHP

```
return $Module->redirectTo( '/setup/rad' );
```

Related

- All views of setup
- The policies of setup
- A custom module and view

Generated by `./console exp:help:examples` from `kernel/setup/module.php`, `kernel/setup/rad.php`. Do not edit this page: change the source and generate again (how). Free documentation: GFDL 1.3 or later.

Exponential Copyright © 1998-2026 Exponential Foundation and 7x
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".
This documentation is free documentation, licensed under the GNU Free Documentation License 1.3 or later:
https://www.gnu.org/licenses/fdl-1.3.html.